APPLE - NO ROAMING FEES SETUP

Apple iPhone WIFI Calling Setup Instructions

Outside the USA – Avoid International Roaming (Optional)

WIFI Calling - Avoid Roaming Fees - There's a great feature available to Ultra Mobile subscribers: WiFi Calling & Text! This allows you to use a WiFi network to make or receive calls and text messages. If you're ever in an area with unpredictable coverage, like a basement, just connect to the nearest WiFi hotspot and use your Ultra Mobile phone to call or text over WiFi! **This also works in most international countries to avoid roaming fees.**

WIFI Compatible Phone List

www.shieldtechsecurity.com/ultramobile-wifi.html



STEP 1



STEP 2



STEP 3



STEP 4

APPLE – USE INTERNATIONAL CELLULAR TOWERS - NEEDS EXTRA ROAMING FEES

Apple iPhone Setup Instructions

https://www.ultramobile.com/setup/iphone

Cellular Towers Outside the USA – Turn on Roaming

Roaming MUST be ENABLED to use cellular phone towers outside the USA.

If enabled, this will require additional roaming charges.

Check Roaming Rates: https://www.ultramobile.com/paygo/international-roaming



STEP 1



STEP 2



STEP 3



STEP 4

AVOID ROAMING FEES!

DO NOT TURN ON ROAMING IF YOU ONLY WANT TO USE WIFI CALLING!

If you plan on keeping a $ balance on your Ultra Mobile account and do NOT want to use cellular towers that charge ROAMING fees, do not enable roaming! Instead, enable the WIFI calling feature.

ANDROID - NO ROAMING FEES SETUP

Android Phone WIFI Calling Setup Instructions

Outside the USA – Avoid International Roaming (Optional)

WIFI Calling - Avoid Roaming Fees - There's a great feature available to Ultra Mobile subscribers: WiFi Calling & Text! This allows you to use a WiFi network to make or receive calls and text messages. If you're ever in an area with unpredictable coverage, like a basement, just connect to the nearest WiFi hotspot and use your Ultra Mobile phone to call or text over WiFi! **This also works in most international countries to avoid roaming fees.**

WIFI Compatible Phone List

www.shieldtechsecurity.com/ultramobile-wifi.html

Samsung Phones

STEP 1



STEP 2



STEP 3

LG Phones

STEP 1



STEP 2

STEP 3

STEP 4

ANDROID – USE INTERNATIONAL CELLULAR TOWERS - NEEDS EXTRA ROAMING FEES

Android Phone Setup Instructions

https://www.ultramobile.com/setup/android

Cellular Towers Outside the USA – Turn on Roaming

Roaming MUST be ENABLED to use cellular phone towers outside the USA.

If enabled, this will require additional roaming charges.

Check Roaming Rates: https://www.ultramobile.com/paygo/international-roaming



STEP 1



STEP 2



STEP 3

AVOID ROAMING FEES!

DO NOT TURN ON ROAMING IF YOU ONLY WANT TO USE WIFI CALLING!

If you plan on keeping a $ balance on your Ultra Mobile account and do NOT want to use cellular towers that charge ROAMING fees, do not enable roaming! Instead, enable the WIFI calling feature.

Android Phone APN Settings

https://www.ultramobile.com/setup/android

Setup Instructions

(complete the steps below after you've inserted your SIM card and activated your plan)

1. Select Settings (located within Apps or the pull-down notifications tray)
2. Select Connections
3. Select Mobile Networks
4. Select Access Point Names
5. Select Add in the upper right hand corner
6. Enter the following information in the fields:

Cellular Data

Name – **Ultra**

APN – **Wholesale**

Proxy – **(leave blank)**

Port – **(leave blank)**

Username & Password – **(leave blank)**

Server – **(leave blank)**

MMS

MMSC – **http://wholesale.mmsmvno.com/mms/wapenc**

Multimedia message proxy – **(leave blank)**

Multimedia message port – **8080**

MCC – **310**

MNC – **260**

Authentication Type – **(leave blank)**

APN Type – **default,supl,mms,ia**

APN Protocol – **IPv4/IPv6**

APN Roaming Protocol – **IPv4**